
Outlook Configuration

I. POP Configuration


- 1) Open Outlook
- 2) Click on File → Account Settings → Add Account



3) Click on New → Manually Configure Server Settings → Next

	Add Account	
Auto Account Setup Manual setup of an account or connect to other server types.		
○ E-mail Account		
Your Name:	Example: Ellen Adams	
E-mail Address:	Example: ellen@contoso.com	
Password: Retype Password:		
Ketype Fassword,	Type the password your Internet service provider has given you.	
Manual setup or ad	ditional server types	
	< Back Next >	

4) As server, choose **POP or IMAP**



5) Fill the e-mail settings as below:

Email Address → enter your email address

Incoming Mail Server:

- Normal Hosting: pop3.cyberia.net.lb
- Panel Hosting: mail.domain.com, example mail.xyz.com


Outgoing Mail Server:

- Normal Hosting: smtp.cyberia.net.lb or bce.idm.net.lb for non-Cyberia connection
- Panel Hosting: mail.domain.com, example mail.xyz.com

Username → enter your email username

Password → enter your email password

6) Click on More Settings



- 7) Click on Outgoing Server
- 8) Check the "My outgoing server (SMTP) requires authentication"
- 9) Choose "logon using"


Username → username@cyberia.net.lb

Password → enter your email password

- 10) Click on Advanced
- 11) Incoming Server (POP3) → 110


Outgoing Server (SMTP) → 25 or 587 for non-Cyberia connection

- 12) Uncheck "Leave a copy of messages on the server"
- 13) Click on OK → Next → Finish → and your email will be configured



II. IMAP Configuration:


- 1) Open Outlook
- 2) Click on File → Account Settings → Add Account



3) Click on New → Manually Configure Server Settings → Next

	Add Account
Auto Account Setup Manual setup of an	account or connect to other server types.
○ E-mail Account	
Your Name:	Example: Ellen Adams
E-mail Address:	Example: ellen@contoso.com
Password: Retype Password:	
кесуре назумоги;	Type the password your Internet service provider has given you.
Manual setup or ad	ditional server types
	< Back Next >

4) As server, choose **POP or IMAP**



5) Fill the e-mail settings as below:

Email Address → enter your email address

Incoming Mail Server:

- Normal Hosting: imap.idm.net.lb
- Panel Hosting: mail.domain.com, example mail.xyz.com

Outgoing Mail Server:

- Normal Hosting: smtp.cyberia.net.lb or bce.idm.net.lb for non-Cyberia connection
- Panel Hosting: mail.domain.com, example mail.xyz.com

Username → enter your email username


Password → enter your email password

6) Click on More Settings

Add New Account

Internet E-mail Settings

Each of these settings are required to get your e-mail account working.



- 7) Click on Outgoing Server
- 8) Check the "My outgoing server (SMTP) requires authentication"
- 9) Choose "logon using"

Username → username@cyberia.net.lb

Password -> enter your email password

- 10) Click on Advanced
- 11) Incoming Server (POP3) → 110

Outgoing Server (SMTP) -> 25 or 587 for non-Cyberia connection

- 12) Uncheck "Leave a copy of messages on the server"
- 13) Click on OK → Next → Finish → and your email will be configured



